

Introduction

This document describes how to import configuration information (airline logos, airline data and aircraft data) designed for Just Flight Traffic Global Early Access into SuperTrafficBoard (STB). The procedure is the same no matter which edition of STB you have, be it FSX, Prepar3D V3 or Prepar3D V4.

Logos

- 1) Download the latest logos package from http://www.supertrafficboard.com/downloads/TrafficGlobal_Logos.zip
- 2) Unzip to a folder of your choice.
- 3) Start STB.
- 4) Configuration -> Settings -> Logos.
- 5) In the "User Logos Path" field, enter the name of the folder you unzipped the logos to:

Deployment | Board Control | Data Interpretation | Columns | Fonts | Colours | Objects | Logos | Commands | Statistics

Use default product logos for:

- Aerosoft/SimMarket MyTrafficX
- Flight1 Ultimate Traffic 2 or Ultimate Traffic Live
- Just Flight TrafficX or TrafficX 360
- ORBX FTX Australia
- World of AI
- Combined MyTrafficX and UT2 or UTLive
- None

Airline Logos

Airline Logo Width: 100 Pixels

Airline Logo Height: 20 Pixels

Airport Logos

Airline Logo Width: 130 Pixels


Airline Logo Height: 48 Pixels

User Logos Path:

- 6) Change the Airline Logo Width to 125 and Airline Logo Height to 25. In the future, all new and updated logos will be supplied at this resolution for better display quality.
- 7) Save your changes.
- 8) Restart STB.

Airline and Aircraft Configuration

- 1) Download the latest configuration files from http://www.supertrafficboard.com/downloads/TrafficGlobal_Configuration.zip
- 2) Unzip to a folder of your choice.
- 3) Start STB.
- 4) Configuration -> Settings -> Objects.



- 5) Click the "Edit Airlines" radio button if not already selected.
- 6) Click "Load Text from File".
- 7) Navigate to the folder you unzipped the files to, and select "Airlines_JustFlight_TrafficGlobal.txt"
- 8) The table is updated with new content and a dialogue confirms the number of entries loaded from file.
- 9) Click the "Edit Aircraft" radio button if not already selected.
- 10) Click "Load Text from File"
- 11) Navigate to the folder you unzipped the files to, and select "Aircraft_JustFlight_TrafficGlobal.txt"
- 12) The table is updated with new content and a dialogue confirms the number of entries loaded from file.
- 13) Save your changes.
- 14) Restart STB.